

Eye-Bit Project Documentation

Generated by Doxygen 1.9.1

1	Интерфейс для создания бита	1
1.0.0.1	Описание:	1
1.0.0.2	Технологии:	1
1.0.0.3	Цель проекта:	1
1.0.0.4	Задачи проекта:	1
1.0.0.5	Запуск:	1
2	Namespace Index	3
2.1	Namespace List	3
3	Hierarchical Index	5
3.1	Class Hierarchy	5
4	Class Index	7
4.1	Class List	7
5	File Index	9
5.1	File List	9
6	Namespace Documentation	11
6.1	Eye-Bit Project Namespace Reference	11
6.2	Eye-Bit Project.Blinking_count Namespace Reference	11
6.2.1	Function Documentation	11
6.2.1.1	blink()	12
6.2.1.2	click()	12
6.2.2	Variable Documentation	12
6.2.2.1	start	12
6.3	Eye-Bit Project.calibration Namespace Reference	12
6.4	Eye-Bit Project.colibrationWithCV Namespace Reference	12
6.4.1	Function Documentation	13
6.4.1.1	click()	13
6.4.1.2	getInhabitationOfPupilsWhenLookingOnScreen()	13
6.4.2	Variable Documentation	13
6.4.2.1	watchsOnPoint	13
6.5	Eye-Bit Project.eye Namespace Reference	14
6.6	Eye-Bit Project.gaze_tracking Namespace Reference	14
6.6.1	Function Documentation	15
6.6.1.1	annotated_frame()	15
6.6.1.2	horizontal_ratio()	15
6.6.1.3	is_blinking()	15
6.6.1.4	is_center()	15
6.6.1.5	is_left()	15
6.6.1.6	is_right()	16
6.6.1.7	landmarks_to_np()	16
6.6.1.8	pupil_left_coords()	16

6.6.1.9	pupil_right_coords()	16
6.6.1.10	pupils_located()	16
6.6.1.11	refresh()	16
6.6.1.12	vertical_ratio()	17
6.6.2	Variable Documentation	17
6.6.2.1	eye_left	17
6.6.2.2	eye_right	17
6.6.2.3	frame	17
6.7	Eye-Bit Project.Interface Namespace Reference	17
6.7.1	Variable Documentation	18
6.7.1.1	app	18
6.7.1.2	w	18
6.8	Eye-Bit Project.listener Namespace Reference	18
6.8.1	Function Documentation	18
6.8.1.1	callback()	18
6.8.1.2	listener()	19
6.8.1.3	play_chord()	19
6.8.2	Variable Documentation	19
6.8.2.1	list_audio	19
6.9	Eye-Bit Project.pupil Namespace Reference	19
6.10	Eye-Bit Project.start_ros Namespace Reference	19
6.10.1	Function Documentation	19
6.10.1.1	run()	20
6.10.1.2	start()	20
6.10.1.3	start_process()	20
6.11	Eye-Bit Project.Trecker_with6acord Namespace Reference	20
6.11.1	Function Documentation	20
6.11.1.1	domain()	20
6.11.1.2	drowLine()	21
6.11.1.3	get_screen_size()	21
6.11.1.4	talker()	22
7	Class Documentation	23
7.1	Eye-Bit Project.calibration.Calibration Class Reference	23
7.1.1	Detailed Description	24
7.1.2	Constructor & Destructor Documentation	24
7.1.2.1	__init__()	24
7.1.3	Member Function Documentation	24
7.1.3.1	evaluate()	24
7.1.3.2	find_best_threshold()	24
7.1.3.3	iris_size()	25
7.1.3.4	is_complete()	25
7.1.3.5	threshold()	25

7.1.4 Member Data Documentation	25
7.1.4.1 nb_frames	25
7.1.4.2 thresholds_left	26
7.1.4.3 thresholds_right	26
7.2 Eye-Bit Project.eye.Eye Class Reference	26
7.2.1 Detailed Description	26
7.2.2 Constructor & Destructor Documentation	27
7.2.2.1 __init__()	27
7.2.3 Member Data Documentation	27
7.2.3.1 blinking	27
7.2.3.2 center	27
7.2.3.3 cods	27
7.2.3.4 frame	27
7.2.3.5 LEFT_EYE_POINTS	27
7.2.3.6 origin	28
7.2.3.7 pupil	28
7.2.3.8 RIGHT_EYE_POINTS	28
7.3 Eye-Bit Project.gaze_tracking.GazeTracking Class Reference	28
7.3.1 Detailed Description	29
7.3.2 Constructor & Destructor Documentation	29
7.3.2.1 __init__()	29
7.3.3 Member Function Documentation	29
7.3.3.1 annotated_frame()	29
7.3.3.2 horizontal_ratio()	29
7.3.3.3 is_blinking()	30
7.3.3.4 is_center()	30
7.3.3.5 is_left()	30
7.3.3.6 is_right()	30
7.3.3.7 pupil_left_coords()	30
7.3.3.8 pupil_right_coords()	30
7.3.3.9 pupils_located()	31
7.3.3.10 refresh()	31
7.3.3.11 vertical_ratio()	31
7.3.4 Member Data Documentation	31
7.3.4.1 calibration	31
7.3.4.2 eye_left	31
7.3.4.3 eye_right	32
7.3.4.4 frame	32
7.4 Eye-Bit Project.Interface.Interface Class Reference	32
7.4.1 Detailed Description	33
7.4.2 Constructor & Destructor Documentation	33
7.4.2.1 __init__()	33
7.4.3 Member Function Documentation	33

7.4.3.1 center()	33
7.4.3.2 count_blinks()	33
7.4.3.3 harm()	33
7.4.3.4 play()	34
7.4.3.5 set_drums()	34
7.4.4 Member Data Documentation	34
7.4.4.1 bass_cb	34
7.4.4.2 beat_button	34
7.4.4.3 buttons_hbox	34
7.4.4.4 cbs_hbox	34
7.4.4.5 const	35
7.4.4.6 drums_cb	35
7.4.4.7 freq	35
7.4.4.8 harm_button	35
7.4.4.9 hihat_cb	35
7.4.4.10 ins_label	35
7.4.4.11 main_vbox	35
7.4.4.12 play_button	35
7.5 Eye-Bit Project.pupil.Pupil Class Reference	36
7.5.1 Detailed Description	36
7.5.2 Constructor & Destructor Documentation	36
7.5.2.1 __init__()	36
7.5.3 Member Function Documentation	37
7.5.3.1 detect_iris()	37
7.5.3.2 image_processing()	37
7.5.4 Member Data Documentation	37
7.5.4.1 iris_frame	37
7.5.4.2 threshold	38
7.5.4.3 x	38
7.5.4.4 y	38
8 File Documentation	39
8.1 __init__.py File Reference	39
8.2 Blinking_count.py File Reference	39
8.3 calibration.py File Reference	39
8.4 colibrationWithCV.py File Reference	40
8.5 eye.py File Reference	40
8.6 gaze_tracking.py File Reference	40
8.7 Interface.py File Reference	41
8.8 listener.py File Reference	42
8.9 pupil.py File Reference	42
8.10 README.md File Reference	42
8.11 start_ros.py File Reference	42

8.12 Trecker_with6acord.py File Reference	43
---	----

Глава 1

Интерфейс для создания бита

1.0.0.1 Описание:

Интерфейс включает в себя камеру для отработки трека взгляда в реальном времени и приложение. Пользователь запускает приложение и на экране появляется панель управления. С помощью взгляда осуществляется задание желаемых параметров, после чего сигнал преобразуется в аудиофайл. Пользователь может скачать полученный файл.

1.0.0.2 Технологии:

- ROS
- Python
- OpenCV

1.0.0.3 Цель проекта:

Реализация интерфейса с функцией Gaze tracking, исследование и применение методов и технологий

1.0.0.4 Задачи проекта:

- Настройка камеры для трека взгляда
- Дизайн приложения
- Разработка алгоритма генерации бита на основе полученных данных
- Разработка приложения

1.0.0.5 Запуск:

Для запуска приложения следует выполнить несколько шагов:

- 1) Клонировать проект в локальный репозиторий
- 2) Запустить файл requirements (для установки необходимых библиотек)
- 3) Переместить содержимое папки src, (папки gaze_tracker и spoproject) в папку, где располагаются ваши ROS пакеты (это может быть catkin_work_space/src)
- 4) в папке ~/catkin_work_space/ выполнить команду catkin_make
- 5) Перейти в папку ~/catkin_work_space/src/spoproject/scripts/
- 6) Запустить интерфейс из этой папки командой python [Interface.py](#)

Глава 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

Eye-Bit Project	11
Eye-Bit Project.Blinking_count	11
Eye-Bit Project.calibration	12
Eye-Bit Project.colibrationWithCV	12
Eye-Bit Project.eye	14
Eye-Bit Project.gaze_tracking	14
Eye-Bit Project.Interface	17
Eye-Bit Project.listener	18
Eye-Bit Project.pupil	19
Eye-Bit Project.start_ros	19
Eye-Bit Project.Trecker_with6acord	20

Глава 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

object	
Eye-Bit Project.calibration.Calibration	23
Eye-Bit Project.eye.Eye	26
Eye-Bit Project.gaze_tracking.GazeTracking	28
Eye-Bit Project.pupil.Pupil	36
QWidget	
Eye-Bit Project.Interface.Interface	32

Глава 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

Eye-Bit Project.calibration.Calibration	
This class calibrates the pupil detection algorithm by finding the best binarization threshold value for the person and the webcam	23
Eye-Bit Project.eye.Eye	
This class creates a new frame to isolate the eye and initiates the pupil detection . . .	26
Eye-Bit Project.gaze_tracking.GazeTracking	
This class tracks the user's gaze	28
Eye-Bit Project.Interface.Interface	
This class is creating GUI for an interaction with a gaze tracker	32
Eye-Bit Project.pupil.Pupil	
This class detects the iris of an eye and estimates the position of the pupil	36

Глава 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

__init__.py	39
Blinking_count.py	39
calibration.py	39
colibrationWithCV.py	40
eye.py	40
gaze_tracking.py	40
Interface.py	41
listener.py	42
pupil.py	42
start_ros.py	42
Trecker_with6acord.py	43

Глава 6

Namespace Documentation

6.1 Eye-Bit Project Namespace Reference

Namespaces

- [Blinking_count](#)
- [calibration](#)
- [colibrationWithCV](#)
- [eye](#)
- [gaze_tracking](#)
- [Interface](#)
- [listener](#)
- [pupil](#)
- [start_ros](#)
- [Trecker_with6acord](#)

6.2 Eye-Bit Project.Blinking_count Namespace Reference

Functions

- def [click](#) (event, x, y, flags, param)
- def [blink](#) ()

The function is intended for counting the number of blinking provides.

Variables

- bool [start](#) = False

6.2.1 Function Documentation

6.2.1.1 blink()

```
def Eye-Bit Project.Blinking_count.blink ( )
```

The function is intended for counting the number of blinking provides.

Returns

:approximate number of blinking provides.

6.2.1.2 click()

```
def Eye-Bit Project.Blinking_count.click (
    event,
    x,
    y,
    flags,
    param )
```

6.2.2 Variable Documentation

6.2.2.1 start

```
bool Eye-Bit Project.Blinking_count.start = False
```

6.3 Eye-Bit Project.calibration Namespace Reference

Classes

- class [Calibration](#)

This class calibrates the pupil detection algorithm by finding the best binarization threshold value for the person and the webcam.

6.4 Eye-Bit Project.colibrationWithCV Namespace Reference

Functions

- def [click](#) (event, x, y, flags, param)
- def [getInhabitationOfPupilsWhenLookingOnScreen](#) (s_w, s_h)

This function is intended for the calibration.

Variables

- bool `watchsOnPoint` = False

6.4.1 Function Documentation

6.4.1.1 `click()`

```
def Eye-Bit Project.colibrationWithCV.click (
    event,
    x,
    y,
    flags,
    param )
```

6.4.1.2 `getInhabitationOfPupilsWhenLookingOnScreen()`

```
def Eye-Bit Project.colibrationWithCV.getInhabitationOfPupilsWhenLookingOnScreen (
    s_w,
    s_h )
```

This function is intended for the calibration.

It provides information about position of pupils on a frame when looking on the define point of the screen. This information is then used for avaluating the size of the domain in which pupils can be and the coordinats of the pupils when looking on the center of the screen.

Parameters

$s \leftrightarrow$ _w	width of the screen;
$s \leftrightarrow$ _h	height of the screen

Returns

:List of the coordinates of pupils corresponding to the following cases: [looking on the center, looking on the top, looking on the right, on the bottom, on the left]

6.4.2 Variable Documentation

6.4.2.1 `watchsOnPoint`

```
bool Eye-Bit Project.colibrationWithCV.watchsOnPoint = False
```

6.5 Eye-Bit Project.eye Namespace Reference

Classes

- class [Eye](#)

This class creates a new frame to isolate the eye and initiates the pupil detection.

6.6 Eye-Bit Project.gaze_tracking Namespace Reference

Classes

- class [GazeTracking](#)

This class tracks the user's gaze.

Functions

- def [pupils_located](#) (self)
Check that the pupils have been located.
- def [refresh](#) (self, [frame](#))
Refreshes the frame and analyzes it.
- def [pupil_left_coords](#) (self)
Returns the coordinates of the left pupil.
- def [pupil_right_coords](#) (self)
Returns the coordinates of the right pupil.
- def [horizontal_ratio](#) (self)
Returns a number between 0.0 and 1.0 that indicates the horizontal direction of the gaze.
- def [vertical_ratio](#) (self)
Returns a number between 0.0 and 1.0 that indicates the vertical direction of the gaze.
- def [is_right](#) (self)
Returns true if the user is looking to the right.
- def [is_left](#) (self)
Returns true if the user is looking to the left.
- def [is_center](#) (self)
Returns true if the user is looking to the center.
- def [is_blinking](#) (self)
Returns true if the user closes his eyes.
- def [annotated_frame](#) (self)
Returns the main frame with pupils highlighted.
- def [landmarks_to_np](#) (landmarks, dtype="int")

Variables

- [eye_left](#)
- [eye_right](#)
- [frame](#)

6.6.1 Function Documentation

6.6.1.1 annotated_frame()

```
def Eye-Bit Project.gaze_tracking.annotated_frame (  
    self )
```

Returns the main frame with pupils highlighted.

6.6.1.2 horizontal_ratio()

```
def Eye-Bit Project.gaze_tracking.horizontal_ratio (  
    self )
```

Returns a number between 0.0 and 1.0 that indicates the horizontal direction of the gaze.

The extreme right is 0.0, the center is 0.5 and the extreme left is 1.0

6.6.1.3 is_blinking()

```
def Eye-Bit Project.gaze_tracking.is_blinking (  
    self )
```

Returns true if the user closes his eyes.

6.6.1.4 is_center()

```
def Eye-Bit Project.gaze_tracking.is_center (  
    self )
```

Returns true if the user is looking to the center.

6.6.1.5 is_left()

```
def Eye-Bit Project.gaze_tracking.is_left (  
    self )
```

Returns true if the user is looking to the left.

6.6.1.6 is_right()

```
def Eye-Bit Project.gaze_tracking.is_right (
    self )
```

Returns true if the user is looking to the right.

6.6.1.7 landmarks_to_np()

```
def Eye-Bit Project.gaze_tracking.landmarks_to_np (
    landmarks,
    dtype = "int" )
```

6.6.1.8 pupil_left_coords()

```
def Eye-Bit Project.gaze_tracking.pupil_left_coords (
    self )
```

Returns the coordinates of the left pupil.

6.6.1.9 pupil_right_coords()

```
def Eye-Bit Project.gaze_tracking.pupil_right_coords (
    self )
```

Returns the coordinates of the right pupil.

6.6.1.10 pupils_located()

```
def Eye-Bit Project.gaze_tracking.pupils_located (
    self )
```

Check that the pupils have been located.

6.6.1.11 refresh()

```
def Eye-Bit Project.gaze_tracking.refresh (
    self,
    frame )
```

Refreshes the frame and analyzes it.

Parameters

<code>:frame</code>	(<code>numpy.ndarray</code>): The frame to analyze
---------------------	--

6.6.1.12 `vertical_ratio()`

```
def Eye-Bit Project.gaze_tracking.vertical_ratio (
    self )
```

Returns a number between 0.0 and 1.0 that indicates the vertical direction of the gaze.

The extreme top is 0.0, the center is 0.5 and the extreme bottom is 1.0

6.6.2 Variable Documentation

6.6.2.1 `eye_left`

`Eye-Bit Project.gaze_tracking.eye_left`

6.6.2.2 `eye_right`

`Eye-Bit Project.gaze_tracking.eye_right`

6.6.2.3 `frame`

`Eye-Bit Project.gaze_tracking.frame`

6.7 Eye-Bit Project.Interface Namespace Reference

Classes

- class `Interface`

This class is creating GUI for an interaction with a gaze tracker.

Variables

- `app` = `QApplication(sys.argv)`
- `w` = `Interface()`

6.7.1 Variable Documentation

6.7.1.1 app

Eye-Bit `Project.Interface.app = QApplication(sys.argv)`

6.7.1.2 w

Eye-Bit `Project.Interface.w = Interface()`

6.8 Eye-Bit `Project.listener` Namespace Reference

Functions

- def [play_chord](#) (n)
The function plays the chord corresponding to the message received.
- def [callback](#) (data)
The callback function of the subscriber.
- def [listener](#) ()
This function sets up the subscriber rosnode "listner" and subscribes on the topik "chatter".

Variables

- list [list_audio](#) = []

6.8.1 Function Documentation

6.8.1.1 `callback()`

```
def Eye-Bit Project.listener.callback (  
    data )
```

The callback function of the subscriber.

6.8.1.2 listener()

```
def Eye-Bit Project.listener.listener ( )
```

This function sets up the subscriber rosnode "listner" and subscribes on the topik "chatter".

6.8.1.3 play_chord()

```
def Eye-Bit Project.listener.play_chord (
    n )
```

The function plays the chord corresponding to the message received.

6.8.2 Variable Documentation

6.8.2.1 list_audio

```
list Eye-Bit Project.listener.list_audio = []
```

6.9 Eye-Bit Project.pupil Namespace Reference

Classes

- class [Pupil](#)

This class detects the iris of an eye and estimates the position of the pupil.

6.10 Eye-Bit Project.start_ros Namespace Reference

Functions

- def [run](#) (cmd, stdout, stderr)
- def [start_process](#) (cmd)
- def [start](#) ()

This function starts roscore, the subscriber node ([listener.py](#)) and the publisher node ([Trecker_with6acord.py](#)) in three parallel subprocesses.

6.10.1 Function Documentation

6.10.1.1 run()

```
def Eye-Bit Project.start_ros.run (
    cmd,
    stdout,
    stderr )
```

6.10.1.2 start()

```
def Eye-Bit Project.start_ros.start ( )
```

This function starts roscore, the subscriber node ([listener.py](#)) and the publisher node ([Trecker_with6acord.py](#)) in three parallel subprocesses.

6.10.1.3 start_process()

```
def Eye-Bit Project.start_ros.start_process (
    cmd )
```

6.11 Eye-Bit Project.Trecker_with6acord Namespace Reference

Functions

- def [get_screen_size](#) (display)
This function provides the width and the height of the screen.
- def [domain](#) (x, y, s_w, s_h)
The function estimates the rectangle that includes the given point.
- def [drawLine](#) (cord, orient, size)
The function provides the coordinates of the line.
- def [talker](#) ()
This function tracks the user's gaze.

6.11.1 Function Documentation

6.11.1.1 domain()

```
def Eye-Bit Project.Trecker_with6acord.domain (
    x,
    y,
    s_w,
    s_h )
```

The function estimates the rectangle that includes the given point.

Parameters

	x and y coordinates of the point and width and height of the screen
--	---

Returns

: integer $0 \leq n \leq 5$

6.11.1.2 drawLine()

```
def Eye-Bit Project.Trecker_with6acord.drawLine (
    cord,
    orient,
    size )
```

The function provides the coordinates of the line.

Parameters

	starting x or y coordinate of the line, orientation (string. "vert" or "hor") and length of the line
--	--

Returns

: list of two points (start and end of the line)

6.11.1.3 get_screen_size()

```
def Eye-Bit Project.Trecker_with6acord.get_screen_size (
    display )
```

This function provides the width and the height of the screen.

Parameters

	object Gdk.Display.get_default()
--	----------------------------------

Returns

: tuple (width, height)

6.11.1.4 talker()

```
def Eye-Bit Project.Trecker_with6acord.talker ( )
```

This function tracks the user's gaze.

First it runs the colibration. Using the information provided by colibration function it estimates the place on the screen where the user is looking. Whith frequency of 10 Hz the function publishes on the topic "chatter" the string representation of integer $0 \leq n \leq 5$ which coresponds to the rectangle in which the user is looking.


Глава 7

Class Documentation

7.1 Eye-Bit Project.calibration.Calibration Class Reference

This class calibrates the pupil detection algorithm by finding the best binarization threshold value for the person and the webcam.

Inheritance diagram for Eye-Bit Project.calibration.Calibration:



Public Member Functions

- def `__init__` (self)
- def `is_complete` (self)
Returns true if the calibration is completed.
- def `threshold` (self, side)
Returns the threshold value for the given eye.
- def `evaluate` (self, eye_frame, side)
Improves calibration by taking into consideration the given image.

Static Public Member Functions

- def `iris_size` (frame)
Returns the percentage of space that the iris takes up on the surface of the eye.
- def `find_best_threshold` (eye_frame)
Calculates the optimal threshold to binarize the frame for the given eye.

Public Attributes

- `nb_frames`
- `thresholds_left`
- `thresholds_right`

7.1.1 Detailed Description

This class calibrates the pupil detection algorithm by finding the best binarization threshold value for the person and the webcam.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 `__init__()`

```
def Eye-Bit Project.calibration.Calibration.__init__ (
    self )
```

7.1.3 Member Function Documentation

7.1.3.1 `evaluate()`

```
def Eye-Bit Project.calibration.Calibration.evaluate (
    self,
    eye_frame,
    side )
```

Improves calibration by taking into consideration the given image.

Parameters

eye_frame	(numpy.ndarray): Frame of the eye
side	Indicates whether it's the left eye (0) or the right eye (1)

7.1.3.2 `find_best_threshold()`

```
def Eye-Bit Project.calibration.Calibration.find_best_threshold (
    eye_frame ) [static]
```

Calculates the optimal threshold to binarize the frame for the given eye.

Parameters

eye_frame	(numpy.ndarray): Frame of the eye to be analyzed
-----------	--

7.1.3.3 iris_size()

```
def Eye-Bit Project.calibration.Calibration.iris_size (
    frame ) [static]
```

Returns the percentage of space that the iris takes up on the surface of the eye.

Parameters

frame	(numpy.ndarray): Binarized iris frame
-------	---------------------------------------

7.1.3.4 is_complete()

```
def Eye-Bit Project.calibration.Calibration.is_complete (
    self )
```

Returns true if the calibration is completed.

7.1.3.5 threshold()

```
def Eye-Bit Project.calibration.Calibration.threshold (
    self,
    side )
```

Returns the threshold value for the given eye.

Parameters

side	Indicates whether it's the left eye (0) or the right eye (1)
------	--

7.1.4 Member Data Documentation

7.1.4.1 nb_frames

Eye-Bit Project.calibration.Calibration.nb_frames

7.1.4.2 thresholds_left

Eye-Bit Project.calibration.Calibration.thresholds_left

7.1.4.3 thresholds_right

Eye-Bit Project.calibration.Calibration.thresholds_right


The documentation for this class was generated from the following file:

- [calibration.py](#)

7.2 Eye-Bit Project.eye.Eye Class Reference

This class creates a new frame to isolate the eye and initiates the pupil detection.

Inheritance diagram for Eye-Bit Project.eye.Eye:



Public Member Functions

- def `__init__` (self, original_frame, landmarks, side, calibration, E_cords)

Public Attributes

- [frame](#)
- [origin](#)
- [center](#)
- [pupil](#)
- [cords](#)
- [blinking](#)

Static Public Attributes

- list [LEFT_EYE_POINTS](#) = [36, 37, 38, 39, 40, 41]
- list [RIGHT_EYE_POINTS](#) = [42, 43, 44, 45, 46, 47]

7.2.1 Detailed Description

This class creates a new frame to isolate the eye and initiates the pupil detection.

7.2.2 Constructor & Destructor Documentation

7.2.2.1 `__init__()`

```
def Eye-Bit Project.eye.Eye.__init__ (
    self,
    original_frame,
    landmarks,
    side,
    calibration,
    E_cords )
```

7.2.3 Member Data Documentation

7.2.3.1 `blinking`

Eye-Bit Project.eye.Eye.blinking

7.2.3.2 `center`

Eye-Bit Project.eye.Eye.center

7.2.3.3 `cods`

Eye-Bit Project.eye.Eye.cods

7.2.3.4 `frame`

Eye-Bit Project.eye.Eye.frame

7.2.3.5 `LEFT_EYE_POINTS`

list Eye-Bit Project.eye.Eye.LEFT_EYE_POINTS = [36, 37, 38, 39, 40, 41] [static]

7.2.3.6 origin

[Eye-Bit](#) `Project.eye.Eye.origin`

7.2.3.7 pupil

[Eye-Bit](#) `Project.eye.Eye.pupil`

7.2.3.8 RIGHT_EYE_POINTS

list [Eye-Bit](#) `Project.eye.Eye.RIGHT_EYE_POINTS = [42, 43, 44, 45, 46, 47]` [static]


The documentation for this class was generated from the following file:

- [eye.py](#)

7.3 Eye-Bit `Project.gaze_tracking.GazeTracking` Class Reference

This class tracks the user's gaze.

Inheritance diagram for `Eye-Bit Project.gaze_tracking.GazeTracking`:



Public Member Functions

- `def __init__ (self)`
- `def pupils_located (self)`
Check that the pupils have been located.
- `def refresh (self, frame)`
Refreshes the frame and analyzes it.
- `def pupil_left_coords (self)`
Returns the coordinates of the left pupil.
- `def pupil_right_coords (self)`
Returns the coordinates of the right pupil.
- `def horizontal_ratio (self)`
Returns a number between 0.0 and 1.0 that indicates the horizontal direction of the gaze.
- `def vertical_ratio (self)`
Returns a number between 0.0 and 1.0 that indicates the vertical direction of the gaze.
- `def is_right (self)`
Returns true if the user is looking to the right.
- `def is_left (self)`
Returns true if the user is looking to the left.
- `def is_center (self)`
Returns true if the user is looking to the center.
- `def is_blinking (self)`
Returns true if the user closes his eyes.
- `def annotated_frame (self)`
Returns the main frame with pupils highlighted.

Public Attributes

- [frame](#)
- [eye_left](#)
- [eye_right](#)
- [calibration](#)

7.3.1 Detailed Description

This class tracks the user's gaze.

It provides useful information like the position of the eyes and pupils and allows to know if the eyes are open or closed

7.3.2 Constructor & Destructor Documentation

7.3.2.1 `__init__()`

```
def Eye-Bit Project.gaze_tracking.GazeTracking.__init__ (
    self )
```

7.3.3 Member Function Documentation

7.3.3.1 `annotated_frame()`

```
def Eye-Bit Project.gaze_tracking.GazeTracking.annotated_frame (
    self )
```

Returns the main frame with pupils highlighted.

7.3.3.2 `horizontal_ratio()`

```
def Eye-Bit Project.gaze_tracking.GazeTracking.horizontal_ratio (
    self )
```

Returns a number between 0.0 and 1.0 that indicates the horizontal direction of the gaze.

The extreme right is 0.0, the center is 0.5 and the extreme left is 1.0

7.3.3.3 is_blinking()

```
def Eye-Bit Project.gaze_tracking.GazeTracking.is_blinking (
    self )
```

Returns true if the user closes his eyes.

7.3.3.4 is_center()

```
def Eye-Bit Project.gaze_tracking.GazeTracking.is_center (
    self )
```

Returns true if the user is looking to the center.

7.3.3.5 is_left()

```
def Eye-Bit Project.gaze_tracking.GazeTracking.is_left (
    self )
```

Returns true if the user is looking to the left.

7.3.3.6 is_right()

```
def Eye-Bit Project.gaze_tracking.GazeTracking.is_right (
    self )
```

Returns true if the user is looking to the right.

7.3.3.7 pupil_left_coords()

```
def Eye-Bit Project.gaze_tracking.GazeTracking.pupil_left_coords (
    self )
```

Returns the coordinates of the left pupil.

7.3.3.8 pupil_right_coords()

```
def Eye-Bit Project.gaze_tracking.GazeTracking.pupil_right_coords (
    self )
```

Returns the coordinates of the right pupil.

7.3.3.9 pupils_located()

```
def Eye-Bit Project.gaze_tracking.GazeTracking.pupils_located (
    self )
```

Check that the pupils have been located.

7.3.3.10 refresh()

```
def Eye-Bit Project.gaze_tracking.GazeTracking.refresh (
    self,
    frame )
```

Refreshes the frame and analyzes it.

Parameters

:frame	(numpy.ndarray): The frame to analyze
--------	---------------------------------------

7.3.3.11 vertical_ratio()

```
def Eye-Bit Project.gaze_tracking.GazeTracking.vertical_ratio (
    self )
```

Returns a number between 0.0 and 1.0 that indicates the vertical direction of the gaze.

The extreme top is 0.0, the center is 0.5 and the extreme bottom is 1.0

7.3.4 Member Data Documentation

7.3.4.1 calibration

Eye-Bit Project.gaze_tracking.GazeTracking.calibration

7.3.4.2 eye_left

Eye-Bit Project.gaze_tracking.GazeTracking.eye_left

7.3.4.3 eye_right

[Eye-Bit Project.gaze_tracking.GazeTracking.eye_right](#)

7.3.4.4 frame

[Eye-Bit Project.gaze_tracking.GazeTracking.frame](#)


The documentation for this class was generated from the following file:

- [gaze_tracking.py](#)

7.4 Eye-Bit Project.Interface.Interface Class Reference

This class is creating GUI for an interaction with a gaze tracker.

Inheritance diagram for Eye-Bit Project.Interface.Interface:



Public Member Functions

- `def __init__ (self)`
- `def center (self)`
Set the main window on the center of screen.
- `def harm (self)`
Launch window for calibration and after that provide special panel with harmonic canvas for making music.
- `def set_drums (self)`
Overlay a drum part on the music file.
- `def count_blinks (self)`
Count user's blinks and set up the frame rate for music file.
- `def play (self)`
Play the finished music file.

Public Attributes

- `play_button`
- `freq`
- `const`
- `beat_button`
- `buttons_hbox`
- `ins_label`
- `drums_cb`
- `hihat_cb`
- `bass_cb`
- `cbs_hbox`
- `harm_button`
- `main_vbox`

7.4.1 Detailed Description

This class is creating GUI for an interaction with a gaze tracker.

It provides main menu with several options for making custom music.

7.4.2 Constructor & Destructor Documentation

7.4.2.1 `__init__()`

```
def Eye-Bit Project.Interface.Interface.__init__ (
    self )
```

7.4.3 Member Function Documentation

7.4.3.1 `center()`

```
def Eye-Bit Project.Interface.Interface.center (
    self )
```

Set the main window on the center of screen.

7.4.3.2 `count_blinks()`

```
def Eye-Bit Project.Interface.Interface.count_blinks (
    self )
```

Count user's blinks and set up the frame rate for music file.

7.4.3.3 `harm()`

```
def Eye-Bit Project.Interface.Interface.harm (
    self )
```

Launch window for calibration and after that provide special panel with harmonic canvas for making music.

7.4.3.4 play()

```
def Eye-Bit Project.Interface.Interface.play (  
    self )
```

Play the finished music file.

It depends on selected options, which file will play.

7.4.3.5 set_drums()

```
def Eye-Bit Project.Interface.Interface.set_drums (  
    self )
```

Overlay a drum part on the music file.

Write result in the result_with_drums.mp3.

7.4.4 Member Data Documentation

7.4.4.1 bass_cb

Eye-Bit Project.Interface.Interface.bass_cb

7.4.4.2 beat_button

Eye-Bit Project.Interface.Interface.beat_button

7.4.4.3 buttons_hbox

Eye-Bit Project.Interface.Interface.buttons_hbox

7.4.4.4 cbs_hbox

Eye-Bit Project.Interface.Interface.cbs_hbox

7.4.4.5 const

Eye-Bit Project.Interface.Interface.const

7.4.4.6 drums_cb

Eye-Bit Project.Interface.Interface.drums_cb

7.4.4.7 freq

Eye-Bit Project.Interface.Interface.freq

7.4.4.8 harm_button

Eye-Bit Project.Interface.Interface.harm_button

7.4.4.9 hihat_cb

Eye-Bit Project.Interface.Interface.hihat_cb

7.4.4.10 ins_label

Eye-Bit Project.Interface.Interface.ins_label

7.4.4.11 main_vbox

Eye-Bit Project.Interface.Interface.main_vbox

7.4.4.12 play_button

Eye-Bit Project.Interface.Interface.play_button


The documentation for this class was generated from the following file:

- [Interface.py](#)

7.5 Eye-Bit Project.pupil.Pupil Class Reference

This class detects the iris of an eye and estimates the position of the pupil.

Inheritance diagram for Eye-Bit Project.pupil.Pupil:



Public Member Functions

- `def __init__ (self, eye_frame, threshold)`
- `def detect_iris (self, eye_frame)`
 Detects the iris and estimates the position of the iris by calculating the centroid.

Static Public Member Functions

- `def image_processing (eye_frame, threshold)`
 Performs operations on the eye frame to isolate the iris.

Public Attributes

- `iris_frame`
- `threshold`
- `x`
- `y`

7.5.1 Detailed Description

This class detects the iris of an eye and estimates the position of the pupil.

7.5.2 Constructor & Destructor Documentation

7.5.2.1 __init__()

```

def Eye-Bit Project.pupil.Pupil.__init__ (
    self,
    eye_frame,
    threshold )
  
```

7.5.3 Member Function Documentation

7.5.3.1 detect_iris()

```
def Eye-Bit Project.pupil.Pupil.detect_iris (
    self,
    eye_frame )
```

Detects the iris and estimates the position of the iris by calculating the centroid.

Returns

:eye_frame (numpy.ndarray): Frame containing an eye and nothing else

7.5.3.2 image_processing()

```
def Eye-Bit Project.pupil.Pupil.image_processing (
    eye_frame,
    threshold ) [static]
```

Performs operations on the eye frame to isolate the iris.

Parameters

eye_frame	(numpy.ndarray): Frame containing an eye and nothing else
threshold	(int): Threshold value used to binarize the eye frame

Returns

:A frame with a single element representing the iris

7.5.4 Member Data Documentation

7.5.4.1 iris_frame

Eye-Bit Project.pupil.Pupil.iris_frame

7.5.4.2 threshold

Eye-Bit Project.pupil.Pupil.threshold

7.5.4.3 x

Eye-Bit Project.pupil.Pupil.x

7.5.4.4 y

Eye-Bit Project.pupil.Pupil.y

The documentation for this class was generated from the following file:

- [pupil.py](#)

Глава 8

File Documentation

8.1 `__init__.py` File Reference

Namespaces

- [Eye-Bit Project](#)

8.2 `Blinking_count.py` File Reference

Namespaces

- [Eye-Bit Project.Blinking_count](#)

Functions

- def [Eye-Bit Project.Blinking_count.click](#) (event, x, y, flags, param)
- def [Eye-Bit Project.Blinking_count.blink](#) ()
The function is intended for counting the number of blinking provides.

Variables

- bool [Eye-Bit Project.Blinking_count.start](#) = False

8.3 `calibration.py` File Reference

Classes

- class [Eye-Bit Project.calibration.Calibration](#)
This class calibrates the pupil detection algorithm by finding the best binarization threshold value for the person and the webcam.

Namespaces

- [Eye-Bit Project.calibration](#)

8.4 colibrationWithCV.py File Reference

Namespaces

- [Eye-Bit Project.colibrationWithCV](#)

Functions

- def [Eye-Bit Project.colibrationWithCV.click](#) (event, x, y, flags, param)
- def [Eye-Bit Project.colibrationWithCV.getInhabitationOfPupilsWhenLookingOnScreen](#) (s_w, s_h)
This function is intended for the calibration.

Variables

- bool [Eye-Bit Project.colibrationWithCV.watchesOnPoint](#) = False

8.5 eye.py File Reference

Classes

- class [Eye-Bit Project.eye.Eye](#)
This class creates a new frame to isolate the eye and initiates the pupil detection.

Namespaces

- [Eye-Bit Project.eye](#)

8.6 gaze_tracking.py File Reference

Classes

- class [Eye-Bit Project.gaze_tracking.GazeTracking](#)
This class tracks the user's gaze.

Namespaces

- [Eye-Bit Project.gaze_tracking](#)

Functions

- def [Eye-Bit Project.gaze_tracking.pupils_located](#) (self)
Check that the pupils have been located.
- def [Eye-Bit Project.gaze_tracking.refresh](#) (self, frame)
Refreshes the frame and analyzes it.
- def [Eye-Bit Project.gaze_tracking.pupil_left_coords](#) (self)
Returns the coordinates of the left pupil.
- def [Eye-Bit Project.gaze_tracking.pupil_right_coords](#) (self)
Returns the coordinates of the right pupil.
- def [Eye-Bit Project.gaze_tracking.horizontal_ratio](#) (self)
Returns a number between 0.0 and 1.0 that indicates the horizontal direction of the gaze.
- def [Eye-Bit Project.gaze_tracking.vertical_ratio](#) (self)
Returns a number between 0.0 and 1.0 that indicates the vertical direction of the gaze.
- def [Eye-Bit Project.gaze_tracking.is_right](#) (self)
Returns true if the user is looking to the right.
- def [Eye-Bit Project.gaze_tracking.is_left](#) (self)
Returns true if the user is looking to the left.
- def [Eye-Bit Project.gaze_tracking.is_center](#) (self)
Returns true if the user is looking to the center.
- def [Eye-Bit Project.gaze_tracking.is_blinking](#) (self)
Returns true if the user closes his eyes.
- def [Eye-Bit Project.gaze_tracking.annotated_frame](#) (self)
Returns the main frame with pupils highlighted.
- def [Eye-Bit Project.gaze_tracking.landmarks_to_np](#) (landmarks, dtype="int")

Variables

- [Eye-Bit Project.gaze_tracking.eye_left](#)
- [Eye-Bit Project.gaze_tracking.eye_right](#)
- [Eye-Bit Project.gaze_tracking.frame](#)

8.7 Interface.py File Reference

Classes

- class [Eye-Bit Project.Interface.Interface](#)
This class is creating GUI for an interaction with a gaze tracker.

Namespaces

- [Eye-Bit Project.Interface](#)

Variables

- [Eye-Bit Project.Interface.app](#) = QApplication(sys.argv)
- [Eye-Bit Project.Interface.w](#) = Interface()

8.8 listener.py File Reference

Namespaces

- [Eye-Bit Project.listener](#)

Functions

- def [Eye-Bit Project.listener.play_chord](#) (n)
The function plays the chord corresponding to the message received.
- def [Eye-Bit Project.listener.callback](#) (data)
The callback function of the subscriber.
- def [Eye-Bit Project.listener.listener](#) ()
This function sets up the subscriber rosnod "listner" and subscribes on the topik "chatter".

Variables

- list [Eye-Bit Project.listener.list_audio](#) = []

8.9 pupil.py File Reference

Classes

- class [Eye-Bit Project.pupil.Pupil](#)
This class detects the iris of an eye and estimates the position of the pupil.

Namespaces

- [Eye-Bit Project.pupil](#)

8.10 README.md File Reference

8.11 start_ros.py File Reference

Namespaces

- [Eye-Bit Project.start_ros](#)

Functions

- def [Eye-Bit Project.start_ros.run](#) (cmd, stdout, stderr)
- def [Eye-Bit Project.start_ros.start_process](#) (cmd)
- def [Eye-Bit Project.start_ros.start](#) ()
This function starts roscore, the subscriber node ([listener.py](#)) and the publisher node ([Trecker_with6acord.py](#)) in three parallel subprocesses.

8.12 Trecker_with6acord.py File Reference

Namespaces

- [Eye-Bit Project.Trecker_with6acord](#)

Functions

- def [Eye-Bit Project.Trecker_with6acord.get_screen_size](#) (display)
This function provides the width and the height of the screen.
- def [Eye-Bit Project.Trecker_with6acord.domain](#) (x, y, s_w, s_h)
The function estimates the rectangle that includes the given point.
- def [Eye-Bit Project.Trecker_with6acord.drowLine](#) (cord, orient, size)
The function provides the coordinates of the line.
- def [Eye-Bit Project.Trecker_with6acord.talker](#) ()
This function tracks the user's gaze.

